







Sniffa Runbook

Adding Policies to a Sensor in the Sensor Manager Application

Serial	Instruction
	<p>Overview.</p> <p>Rules Policies consist of 1 or more Snort™ rules that are grouped together based upon a common attribute, e.g. Application, Protocol, Attack Type, etc.</p> <p>1 or more Snort™ rules policies can be added to a Sensor’s configuration file and stored in the Sensor Manager Application database.</p> <p>All of the Snort™ rules that are included in a Sensor’s configuration file, will be deployed out to the network Sensor at deployment time.</p> <p>Snort™ rules policies can be added to Sensors in 2 ways:</p> <ul style="list-style-type: none"> • Via the Rules Management Panel (serial 1 onwards). • Via the Sensor Management Panel (serial 10 onwards). <p>This runbook includes the tasks to be completed, to add Snort™ rules policies to a Sensor in the Sensor Manager Application.</p>
1.	<p>Adding policies via the Rules Management Panel.</p> <p>Go to the Admin panel. Select the ‘Configure’ menu item. Select the ‘Snort™ Rules’ menu item.</p> 
2.	<p>Select the ‘Options’ menu item. Select the ‘Rule Policies’ menu item.</p> 





Sniffa Runbook

Adding Policies to a Sensor in the Sensor Manager Application

<p>3.</p>	<p>Adding multiple polices to a single Sensor.</p> <p>Highlight one Sensor from the list in the left-hand table, using the left mouse button.</p>	
<p>4.</p>	<p>Highlight 1 or more of the Rule Policies from the right-hand table, using the left mouse button.</p> <p><i>Note:</i> Use the 'Shift' or 'Ctrl' button in conjunction with the left mouse button to select multiple polices.</p>	
<p>5.</p>	<p>Click on the button marked with the left arrow, to add the selected polices to the selected Sensor.</p> <p>Selected polices should appear in the middle table.</p>	
<p>6.</p>	<p>Adding a single policy to multiple Sensors.</p> <p>Select the 'Options' menu item. Select the 'Switch View' menu item.</p>	





Sniffa Runbook

Adding Policies to a Sensor in the Sensor Manager Application

<p>7.</p>	<p>Highlight one Policy from the list in the left-hand table, using the left mouse button.</p>	
<p>8.</p>	<p>Highlight 1 or more of the Sensor from the right-hand table, using the left mouse button.</p> <p><i>Note:</i> Use the 'Shift' or 'Ctrl' button in conjunction with the left mouse button to select multiple Sensors.</p>	
<p>9.</p>	<p>Click on the button marked with the left arrow, to add the selected Sensors to the selected Policy.</p> <p>Selected Sensors should appear in the middle table.</p>	
<p>10.</p>	<p>Adding policies via the Sensor Management Panel.</p> <p>Go to the Admin panel. Select the 'Configure' menu item. Select the 'Sensors' menu item.</p>	

Sniffa Runbook

Adding Policies to a Sensor in the Sensor Manager Application

<p>11.</p>	<p>Right click on a Sensor and select 'Snort™' and then select the 'Policies' menu item.</p>	
<p>12.</p>	<p>Highlight 1 or more policies from the left-hand table, using the left mouse button.</p> <p><i>Note:</i> Use the 'Shift' or 'Ctrl' button in conjunction with the left mouse button to select multiple Sensors.</p>	
<p>13.</p>	<p>Click on the button marked with the right arrow, to add the selected policies to the Sensor.</p> <p>Selected policies should appear in the right-hand table.</p>	
<p>14.</p>	<p>Click on the cross at the top right-hand corner to close the policies window.</p>	
<p>15.</p>	<p>End of Runbook.</p>	